

# Provision RabbitMQ



**Menu:** Comms / RabbitMQ (Provision)



**Feature:** AWS Core



**Editions:** Cloud, Corporate, Store

This feature is for development preview only. It is not intended for production, QA, or demonstration at this time.

Kensium POS uses the RabbitMQ message broker to coordinate communication amongst an organization's POS servers and tenants. RabbitMQ Provisioning ensures that the necessary RabbitMQ components are configured to enable this communication.

The provisioning process requires that you enter access and credential information for the RabbitMQ servers that should have been installed along with POS. For instructions on how to install RabbitMQ, see the following topics:

- [AWS \(Hub\) Installation](#)
- [On-site Installation](#)

All tenants will provision components in the hub RabbitMQ server. Additionally, corporate and store tenants also require an on-site (local) RabbitMQ server, and will provision components in that local server.

Most provisioning details are handled by POS automatically. See [RabbitMQ Provisioning](#) for a detailed reference on how the components are provisioned.

## 1) Skip Provisioning

You can skip provisioning (e.g. during setup) if you know that provisioning has already been performed.



However, it is not a problem to run provisioning multiple times.

## 2) Local Node

Local node settings are only shown for corporate and store tenants. Cloud tenants do not communicate with a local RabbitMQ server.

### Host

Enter the host name for the local RabbitMQ server. This is `localhost` if RabbitMQ is installed on the same server as POS, or another host name of a server within the corporate or store LAN.

### Port

This value refers to the TCP/IP port where RabbitMQ communications take place. This is typically 5672 but may differ according to your RabbitMQ server settings.

### Admin Port

This value refers to the TCP/IP port where RabbitMQ management tasks are performed. This is typically 15672 but may differ according to your RabbitMQ server settings.

### Use SSL

Check this value if communications to RabbitMQ should be protected by secure sockets layer (SSL). This is typically unchecked for the local RabbitMQ server, but may differ according to your RabbitMQ server settings.

It's recommended to use SSL on your local network, but this step requires additional configuration of SSL certificates on your local RabbitMQ server.

### Admin User & Password

These credentials refer to your local RabbitMQ administrator username and password. They are used



only during provisioning to create the necessary RabbitMQ components, and are not stored outside the provisioning process.

#### **Password**

Provisioning creates a non-administrative RabbitMQ user account for the sole purpose of sending messages via the local RabbitMQ server. You must enter a password for this account.

Use the Kensium password manager to generate and record a secure, random password value.

If provisioning detects that the user account already exists, its password will be **updated** to the value you enter here.

### **3) Hub Node**

Hub node settings are show for all tenant types, and correspond to the hub RabbitMQ server which are typically installed in the Kensium cloud.

#### **Host**

Enter the host name for the hub RabbitMQ server.

#### **Port**

This value refers to the TCP/IP port where RabbitMQ communications take place. This is typically 5671 but may differ according to your hub RabbitMQ server settings.

#### **Admin Port**

This value refers to the TCP/IP port where RabbitMQ management tasks are performed. This is typically 443 but may differ according to your RabbitMQ server settings.

#### **Use SSL**

Check this value if communications to RabbitMQ should be protected by secure sockets layer (SSL). This is typically checked for the hub RabbitMQ server.



It's highly recommended to use SSL for the hub RabbitMQ server, as communication is typically performed over the public internet.

#### Admin User & Password

These credentials refer to your hub RabbitMQ administrator username and password. They are used only during provisioning to create the necessary RabbitMQ components, and are not stored outside the provisioning process.

#### Password

Provisioning uses a non-administrative RabbitMQ user account for the sole purpose of routing messages to and from local RabbitMQ servers via the hub RabbitMQ server. This user account is shared amongst all of your organization's tenants.

You must enter the password for this account.

#### Create Hub Node & User

This option should be selected if this is the first time you are provisioning the hub RabbitMQ server. Selecting this option will ensure that necessary shared components are created, including the user account used for normal communications.

If this option is selected, the password you enter above will be used to create or update this user account's password.

Use the Kensium password manager to generate and record a secure, random password value.

If provisioning detects that the user account already exists, its password will be **updated** to the value you enter here. The changed password is **not** communicated to other tenants that use the original password.



For this reason, you must re-provision – and supply the new password – to any tenants that are configured with the original password.

