




Pick, Pack & Ship with Cross Dock

 Two elements of KensiumWMS Advanced interplay with Cross-Dock when working with Open Shipments.

1. Zone Picking: A properly configured WMS will separate a pick list by zone. The WMS handheld operator can select a particular zone they are working in. With this, the Next Shipment function on the handheld will only present shipments with items to be picked from the selected zone.



2. Staging Location. A staging location for any shipment may be identified in Acumatica or on the handheld. Once established, this location will appear any time that shipment is loaded into the handheld. This is not a location defined in Acumatica. It is simply a reference used to rejoin separate zone picks.



Shipments

CONFIRM SHIPMENT

HOLD

PRINT CONTAINERS LABELS

Shipment Nbr.: 005132

Type: Shipment

Status: Open

Operation: Issue

Shipment Date: 6/29/2024

Customer: ACTIVESTAF - Active Staffing Service

Location: MAIN - Primary Location

Warehouse ID: WHOLESALE - Wholesale Warehouse

Order Priority: 3 - Standard

Workgroup: Solution Sales

Owner: Jay Parker

Shipped Quantity: 10.00

Shipped Weight: 172.300000

Shipped Volume: 200.000000

Packages: 0

Package Weight: 0.000000

Pick Status: Open

Staging Location: A24

Description:

DETAILS

ORDERS

SHIPPING

ADDRESSES

PACKAGES

FUSION INNER PACKS DETAIL

LINE DETAILS

ADD ORDER

INVENTORY SUMMARY

SET SHIPPED QTY TO PACKED QTY

BaseOriginal	Order Type	Order Nbr.	Inventory ID	Free Item	Location	UOM	Shipped Qty.	Ordered Qty.	Open Qty.
10.000000	SO	SO007558	CONAIRT1		R1S1	EA	10.00	10.00	0.00

Summit 7.0.0.9 Android 7

App Center

2:30

Pick

Enter shipment #: 005132

Staging Location: A24

Enter manual quantity

PICK ITEMS

COMMIT

REVIEW

CANCEL

Using these functions, affected shipments may be picked and staged pending receipt of new inventory needed to fill the order. By setting up the cross-dock location as a separate zone, when the cross-dock is complete, and the shipment updated the handheld operator can select the cross-dock zone to load only shipments to which the new inventory has been allocated. They will also see the location of those staged shipments. In this manner, they may easily add the inventory to the staged shipments for final packing and shipping.

Production and Cross-Dock

KensiumWMS Cross-Dock can also be used to facilitate manufacturing by easily identifying items missing from open shipments due to stockouts. The Cross-dock Open Shipments GI identifies items and quantities needed to fill open shipments.